


To upgrade a Windows Mobile 6.5 PDA to HTC Email Powered by Google™

1. Touch 'Start'.




3. Touch 'E-mail'.




2. Touch 'Messaging'.




4. Touch the sccoast.net email account.




5. Once the email inbox is open, touch 'Menu'.




7. Touch 'Options'.




6. Scroll down in the menu and touch 'Tools'.



8. Press and hold on the sccoast.net email account.



9. Touch 'Delete'.



12. Touch 'Messaging'.




10. Exit to device home screen.


11. Touch 'Start'.



13. Touch 'Mail Setup'.




14. Enter email address and password, then touch 'Next'.




The screenshot shows the 'Mail Setup' screen. At the top, there is a title bar with 'Mail Setup' and several icons. Below the title bar, the text 'Mail Setup' is displayed. The main content area contains two input fields: 'Email address:' with the text 'customer@sccoast.net' and 'Password:' with a masked password '*****'. There is a checkbox for 'Exchange Email (Outlook)' which is unchecked, and a checkbox for 'Save password' which is checked. At the bottom, there are three buttons: 'Cancel', a keyboard icon, and 'Next'.

15. Enter customer name, and touch 'Next'.




The screenshot shows the 'Mail Setup' screen. At the top, there is a title bar with 'Mail Setup' and several icons. Below the title bar, the text 'Mail Setup' is displayed. The main content area contains two input fields: 'Your name:' with the text 'Customer Name' and 'Account display name:' with the text 'sccoast.net'. There is a note below the 'Account display name' field: 'The name for this account on this device.' At the bottom, there are three buttons: 'Back', a keyboard icon, and 'Next'.

16. Enter 'Incoming mail server' as pop.gmail.com and change 'User name' to full sccoast.net email address. Password should already be populated. Then touch 'Next'.




The screenshot shows the 'Mail Setup' screen. At the top, there is a title bar with 'Mail Setup' and several icons. Below the title bar, the text 'Mail Setup' is displayed. The main content area contains several fields: 'Incoming mail server:' with the text 'pop.gmail.com', 'Account type:' with a dropdown menu showing 'POP3', 'User name:' with the text 'customer@sccoast.net', and 'Password:' with a masked password '*****'. There is a checkbox for 'Save password' which is checked. At the bottom, there are three buttons: 'Back', a keyboard icon, and 'Next'.

17. Enter 'Outgoing mail server' as cwmx.com and touch 'Next'.



The screenshot shows the 'Mail Setup' screen. At the top, there is a title bar with 'Mail Setup' and several icons. Below the title bar, the text 'Mail Setup' is displayed. The main content area contains one input field: 'Outgoing (SMTP) mail server:' with the text 'cwmx.com'. There are two checkboxes: 'Outgoing server requires authentication' which is unchecked, and 'Use the same user name and password for sending email' which is checked. At the bottom, there are three buttons: 'Back', a keyboard icon, and 'Next'.

18. Touch the drop-down menu to adjust how often the device should automatically check for new email. Touch 'Done.'




19. Touch 'Start'.




20. Touch 'Messaging'.




21. Touch 'E-mail'.




22. Touch the sccoast.net email account.




24. Scroll down in the menu and touch 'Tools'.




23. Once the email inbox is open, touch 'Menu'.




25. Touch 'Options'.




26. Touch the sccoast.net email account.




28. Touch 'Next'.



27. Touch 'Edit Account Setup'.



29. Touch 'Next'.



30. Touch 'Next'.

Messaging

E-mail Setup

Incoming mail server:
pop.gmail.com
If unsure, check with your provider to get POP/IMAP settings.

Account type:
POP3

Previous Next

32. Touch 'Advanced Server Settings'.

Messaging

E-mail Setup

Outgoing (SMTP) mail server:
cwmx.com

Outgoing server requires authentication

Use the same user name and password for sending e-mail

Advanced Server Settings

Previous Next

31. Touch 'Next'.

Messaging

E-mail Setup

User name:
customer@sccoast.net
(Examples: kevinc, domain\kevinc, kevinc@contoso.com, etc.)

Password:

Save password

Previous Next

33. Check the box for 'Require SSL for Incoming e-mail'. Then touch 'Done'.

Messaging

E-mail Setup

Advanced Server Settings


Require SSL for Incoming e-mail

Require SSL for Outgoing e-mail


Network connection:
The Internet

Done Cancel

34. Back on the 'Outgoing mail server' screen, click 'Next'.



36. To complete email setup, touch 'Finish'.



35. Touch 'Next'.

