


## To set up a Windows Mobile 6.5 PDA w/ HTC Email Powered by Google™

1. Touch 'Start'.




3. Touch 'Mail Setup'.



2. Touch 'Messaging'.



4. Enter email address and password, then touch 'Next'.



5. Enter customer name, and touch 'Next'.

The screenshot shows the 'Mail Setup' screen. At the top, there is a title bar with 'Mail Setup' and several icons. Below the title bar, the text 'Mail Setup' is displayed. The main content area contains the following fields and options:

- 'Your name:' followed by a text input field containing 'Customer Name'. A red box highlights this field. Below it, the text '(Example: Kevin Cook)' is shown.
- 'Account display name:' followed by a text input field containing 'sccoast.net'.
- Below the input field, the text 'The name for this account on this device.' is displayed.

At the bottom of the screen, there is a black bar with two buttons: 'Back' and 'Next'. The 'Next' button is highlighted with a red border.

7. Enter 'Outgoing mail server' as cwmx.com and touch 'Next'.

The screenshot shows the 'Mail Setup' screen. At the top, there is a title bar with 'Mail Setup' and several icons. Below the title bar, the text 'Mail Setup' is displayed. The main content area contains the following fields and options:

- 'Outgoing (SMTP) mail server:' followed by a text input field containing 'cwmx.com'. A red box highlights this field.
- Below the input field, there are two checkboxes:
  - An unchecked checkbox labeled 'Outgoing server requires authentication'.
  - A checked checkbox labeled 'Use the same user name and password for sending email'.

At the bottom of the screen, there is a black bar with two buttons: 'Back' and 'Next'. The 'Next' button is highlighted with a red border.

6. Enter 'Incoming mail server' as pop.gmail.com and change 'User name' to full sccoast.net email address. Password should already be populated. Then touch 'Next'.

The screenshot shows the 'Mail Setup' screen. At the top, there is a title bar with 'Mail Setup' and several icons. Below the title bar, the text 'Mail Setup' is displayed. The main content area contains the following fields and options:

- Text: 'Enter the mail settings from your service provider.'
- 'Incoming mail server:' followed by a text input field containing 'pop.gmail.com'. A red box highlights this field.
- 'Account type:' followed by a dropdown menu showing 'POP3'.
- 'User name:' followed by a text input field containing 'customer@sccoast.net'. A red box highlights this field.
- 'Password:' followed by a text input field containing '\*\*\*\*\*'.
- A checked checkbox labeled 'Save password'.

At the bottom of the screen, there is a black bar with two buttons: 'Back' and 'Next'. The 'Next' button is highlighted with a red border.

8. Touch the drop-down menu to adjust how often the device should automatically check for new email. Touch 'Done.'

The screenshot shows the 'Mail Setup' screen. At the top, there is a title bar with 'Mail Setup' and several icons. Below the title bar, the text 'Mail Setup' is displayed. The main content area contains the following fields and options:


- 'Automatic send/receive:' followed by a dropdown menu showing 'Every 15 minutes'.
- 'Advanced settings:' followed by two checkboxes:
  - A checked checkbox labeled 'Send/receive when I click Send'.
  - An unchecked checkbox labeled 'Use automatic send/receive schedule when roaming'.

At the bottom of the screen, there is a black bar with two buttons: 'Back' and 'Done'. The 'Done' button is highlighted with a red border.

9. Touch 'Start'.




11. Touch 'E-mail'.




10. Touch 'Messaging'.




12. Touch the sccoast.net email account.




13. Once the email inbox is open, touch 'Menu'.




15. Touch 'Options'.




14. Scroll down in the menu and touch 'Tools'.




16. Touch the sccoast.net email account.



17. Touch 'Edit Account Setup'.




19. Touch 'Next'.



18. Touch 'Next'.



20. Touch 'Next'.



21. Touch 'Next'.

Messaging

E-mail Setup

**User name:**  
customer@sccoast.net  
(Examples: kevinc, domain\kevinc,  
kevinc@contoso.com, etc.)

**Password:**  
\*\*\*\*\*

Save password

Previous Next

23. Check the box for 'Require SSL for Incoming e-mail'. Then touch 'Done'.

Messaging

E-mail Setup

**Advanced Server Settings**

Require SSL for Incoming e-mail

Require SSL for Outgoing e-mail

**Network connection:**  
The Internet

Done Cancel

22. Touch 'Advanced Server Settings'.

Messaging

E-mail Setup

**Outgoing (SMTP) mail server:**  
cwmx.com

Outgoing server requires authentication

Use the same user name and password  
for sending e-mail

[Advanced Server Settings](#)

Previous Next

24. Back on the 'Outgoing mail server' screen, click 'Next'.

Messaging

E-mail Setup

**Outgoing (SMTP) mail server:**  
cwmx.com


Outgoing server requires authentication

Use the same user name and password  
for sending e-mail

[Advanced Server Settings](#)

Previous Next

25. Touch 'Next'.



26. To complete email setup, touch 'Finish'.

